

# トイレットペーパーに字を書く筆圧でASCIIコード表

<http://tp.yockow.net/~page/individual/00000001.html> 付録

下位4ビット 上位3ビット	0	1	2	3	4	5	6	7	8	9	A	B	C	D	E	F
0	NUL	SOH	STX	ETX	EOT	ENQ	ACK	BEL	BS	HT	LF/NL	VT	FF	CR	SO	SI
1	DLE	DC1	DC2	DC3	DC4	NAK	SYN	ETB	CAN	EM	SUB	ESC	FS	GS	RS	US
2	SP	!	“	#	\$	%	&	‘	(	)	*	+	,	-	.	/
3	0	1	2	3	4	5	6	7	8	9	:	;	<	=	>	?
4	@	A	B	C	D	E	F	G	H	I	J	K	L	M	N	O
5	P	Q	R	S	T	U	V	W	X	Y	Z	[	\	]	^	_
6	`	a	b	c	d	e	f	g	h	i	j	k	l	m	n	o
7	p	q	r	s	t	u	v	w	x	y	z	{		}	~	DEL

NUL: null  
SOH: Start Of Heading  
STX: Start Of Text  
ETX: End Of Text  
EOT: End Of Transmission  
ENQ: Enquiry  
ACK: Acknowledge  
BEL: Bell  
BS: Backspace  
HT: Horizontal Tab  
LF/NL: NL Line Feed, New Line  
VT: Vertical Tab

FF: NP Form Feed, new page  
CR: Carriage Return  
SO: Shift Out  
SI: Shift In  
DLE: Data Link Escape  
DC1: Device Control 1  
DC2: Device Control 2  
DC3: Device Control 3  
DC4: Device Control 4  
NAK: Negative Acknowledge  
SYN: Synchronous Idle  
ETB: End Of Trans. Block

CAN: Cancel  
EM: End Of Medium  
SUB: Substitute  
ESC: Escape  
FS: File Separator  
GS: Group Separator  
RS: Record Separator  
US: Unit Separator  
SP: Space  
DEL: Delete